

# Git Workflows

You can perform many common Git workflows from within Design Center. Most of these are performed with the [Repo Browser](#) and [Source Control Panel](#), both of which are available in the main navigation bar.

## Navigating Repositories

You can navigate the Git repositories connected to your AtScale account from the **Repo Browser** panel.

At the top of the panel, you can use the **Repo** and **Branch** fields to switch between repositories and branches.

In the **Workspace** area, you can drill down through the individual folders within the repository. You can also click the menu icons next to individual files and folders to duplicate, edit, and delete them as needed.

## Syncing

Syncing with the remote repository ensures that changes made by other users are available in your local copy.

To sync with the remote repository, open the **Source Control** panel and click **Sync** at the bottom of the panel. You can also click the sync icon at the top of the panel.

## Reverting Changes

If you have local changes you no longer want, you can revert them from the **Source Control** panel.

To revert local changes:

1. In the main navigation bar, click the **Source Control** icon. The **Source Control** panel opens.
2. Expand the **Workspace Changes** section.
3. Do one of the following:
  - ▲ To revert a single change, click the change's context menu and select **Revert change**.
  - ▲ To revert multiple specific changes, select them in the list, then click the context menu for the workspace and select **Revert selected**.
  - ▲ To revert all changes, click the context menu for the workspace and select **Revert all**.

The changes are undone and no longer appear in the **Workspace Changes** area.

## Viewing Diffs

If you have made changes locally and want to view exactly what you modified before committing, you can view the diff between the original and modified versions of the file.

To view the diff for a changed file:

1. In the main navigation bar, click the **Source Control** icon. The **Source Control** panel opens.
2. Expand the **Workspace Changes** section.
3. Click the menu icon next to the change you want to view and select **Diff against latest changes**.

The **Diff Editor** opens for the selected file.

## Committing Changes

You can perform local commits from the **Source Control** panel.

To commit your changes:

1. In the main navigation bar, click the **Source Control** icon. The **Source Control** panel opens.
2. Expand the **Workspace Changes** section.
3. Select the changes you want to commit. The **Commit Message** section appears at the bottom of the panel.
4. Enter a commit message and click **Local Commit**.
5. To push your changes to the remote repository, click **Sync**.